

FreeForm - Quick Entry Dimensions

Dimension Quick Entry

Option is only available with FreeForm 📴 and when ...

- View Options Construction (radio button)
- Edit Option Dimensions is ticked

Dimension Quick Entry

Base Line Width -- sets the width of the initial Base Line, shown as a dashed line in the preview pane, which determines the width of the root section.

This value may be used to *scale the entire box* if the required stretch options are used (see FreeForm Tutorial 104 Simple Scale & Stretch Modes). Changing this value after the box is

illustrated requires rescaling the Flexi artwork. **Example**: This box has been enlarged by changing the Base Line Width from 200mm to 1400mm.

Edit fields and **More button** -- used for entering scaling. Parameters may be for immediate use with the 1...9 numeric **shortcut keys**, or may be used for parametrising a basic design for creating different sized boxes. Note that in the latter case changes in scaling may require re-illustrating the box.

Boxes 1-9 can be used for the many repeatable dimensions that might be used throughout the building of your freeform box. For example, panel widths, flap lengths, chamfers and fillet corners. These dimensions are used in conjunction the construction tools.


The **More** button allows you to extend the use of the 1-9 input controls. See next page.

Watch related Video

- (1) Set Base Line Width
- (2) Enter Quick Entry Dims
- (3) Right click on Base Line to bring up context menu and select 'At Line' then fly out 'Add Basic Flap'
 - NB: Hot Keys allow you to use the <u>L</u> key for Line and the <u>F</u> key for Flap
- (4) Press a Quick Entry number to achieve required height, all three shown in diagram
- (5) Left click to hold the dimension required.

SAI Box and Display - Untitled 1		$=$ \Box x
Description Code FreeForm Info Add to User Library Catalog FREEFORM Style Standard	A Right Click	
Description Free Form Template View Options	Add Points Before B Add Points After A Delete Point D Drag Point G At Point P	
Materials Send to Flexi Send Box Double Sided	At Line L Add Basic Flap E At Machine Step M Paste Clipboard Section ¥ At Section S Paste Clipboard Subtree	
Dimension Quick Entry More (1) Base Line Width 300mm More (2) (1) 200mm (2) 100mm (3) 50mm (4) (5) (6) (6) (7) (8) (9) (9)	(4) (1) 200mm (2) 100mm Undo/Redo	(5) Left Click To Hold Dimensions (3) 50mm
	✓ Active Section	🔒 🕂 -290.6, 351.3 💮 👻


Dimension Quick Entry					
Base Line Width		300mm		Mo	re
(1)		(2)		(3)	
(4)		(5)		(6)	
(7)		(8)		(9)	



Dimension Quick Entry				
Base Line Width	1400mm	More		

Alternate way to set height is to ...

- Right click **Base Line** to bring up context menu
 - and select 'At Line'
 - then fly out 'Add Basic Flap'
- Press the 'full stop' key to open the Section Height dialog which will show current height.
- Change height as required
- Click 'Apply'



The **More** button in this section opens a dialog box that lets you extend the use of the 1-9 input controls. The use of this dialog is discussed in **FreeForm Tutorial 105 – Parametric Scaling**.

Catalog FREEFOR	RM Style	Standard	Advanced	d Edit Proper	ties				×
Description Free Form Template		Dimension setup							
View Options	◯ 3D	uction	Forced:	Name	Value	Formula			ectRatio
Edit Options		● 1○ 0	B	200mm					
Materials	Materials 🔽 Dimensions 🗌 Textures		○2 ○3						
Send to Flexi Send Box Double Sided		04							
		05	BoxHt	300mm					
Dimension Quick Entry		06	BoxDp	200mm	1				
Base Line Width	200mm	More	07	FlapHt	70mm				
(1) 200mm	(2)	(3)	08	GlueHt	40mm				
(4)	(5)	(6)	9						
(7)	(8)	(9)							
			Current Value:		200mm				
							. 1		. 1
					OK	Ca	incel	Ар	ply



FOR ALL TUTORIALS REFER TO SAI BOX & DISPLAY USER GUIDE

